

# 5 Step Trimming Process


## FUNCTIONAL TRIMMING




1. Make the inner (Medial) claw 7.5cm long. Leave 5–7 mm thickness in the tip of the toe. Spare the height of the heel.

2. Make the outer (Lateral) claw equally long and bearing surface equally high as the inner claw (if possible).

3. Make a slope (scallop out) in the soles.




## CURATIVE TRIMMING



4. If one of the claws is damaged (often the outer claw) lower this claw towards the heel 2/3 of the sole, if possible. The weight is now partly transferred to the sound claw.

If the damaged claw is still bearing too much weight, apply a claw block to the sound claw.

5. Remove loose horn and trim down hard ridges.



“Raising the standard of hoof care”